

caribou3d

05_Upgrade Duet Web Control (DWC)

Written By: Caribou3d


The screenshot displays the CaribouDuet web control interface. The top navigation bar includes a menu icon, the title 'CaribouDuet', a 'Send code...' input field with a 'SEND' button, an 'UPLOAD & START' button, and a red 'EMERGENCY STOP' button. The left sidebar contains a list of controls: Control (selected), Dashboard, Console, Height Map, Job, Status, Files, Display, Filaments, Jobs, Macros, System, Settings, and General. The main content area is divided into several sections:

- Status Panel:** Shows 'Status' as 'Off' and 'Mode' as 'FFF'. It includes a 'Tool Position' table with X (0.0), Y (0.0), and Z (0.0) coordinates. Below this is an 'Extruder Drives' section showing 'Drive 0' at 0.0. A 'Speeds' section shows 'Requested Speed' at 0 mm/s and 'Top Speed' at 0 mm/s. A 'Sensors' section shows 'Vin' at 1.7 V and 'MCU Temperature' at 25.1 C.
- Tools Panel:** Displays 'Tools + Extra' and 'Control All'. It shows 'No Tools' with an information icon.
- Temperature Chart:** Shows 'No Data' with an information icon.
- Machine Movement Panel:** Features a 'HOME ALL' button, a 'Machine Movement' section with 'HOME X', 'HOME Y', and 'HOME Z' buttons, and a 'COMPENSATION & CALIBRATION' dropdown. Below these are tables of movement commands (e.g., X-50, X-10, X-1, X-0.1, X+0.1, X+1, X+10, X+50) and a warning: 'The following axes are not homed: X, Y, Z'.
- Extrusion Control Panel:** Includes 'Extrusion Control' with 'Feed amount in mm' (100, 50, 20, 10, 5, 1) and 'Feedrate in mm/s' (60, 30, 15, 5, 1) sliders.
- Macros Panel:** Shows a list of macros under 'Root', including '01-Test_IR_PD_Ho...', '02-Test_Fans', '03-Test_Heaters', '04-Test_motors', 'SETNETWORK14', and 'SETNETWORK24'.

INTRODUCTION


Diese Anleitung beschreibt, wie man die Software für Duet Web Control aktualisiert

Step 1 — Überprüfen der installierten Version




- Wählen Sie in dem Duet Web Control folgende Schaltflächen aus:
 - Settings
 - General
 - ablesen der installierten Version

Step 2 — Überprüfen der aktuellen Version




- Prüfen Sie die aktuelle Versionsnummer aus dem [CaribouDuet Software Verzeichnis](#).
- Klicken Sie in dem Dateimanager auf der Website folgende Schaltflächen aus:
 - Duet Web Control
 - 01_Latest Version x.x
- ① x.x ist ein Platzhalter für die Versionsnummer. Zum Zeitpunkt der Erstellung des Manuals, war die aktuellste Version "3.2".
- Sofern die Versionsnummer höher ist, als die bei Ihnen installierte Version, laden die die Datei **DuetWebControl-SD.zip** runter.

Step 3 — Upload der Systemdaten für DWC



- Wählen Sie in dem Duet Web Control folgende Schaltflächen aus:
 - Files
 - System
 - Update System Files
- Wählen Sie nun die zuvor heruntergeladene Datei "**DuetWebControl-SD.zip**" und bestätigen sie den Upload mit "open".
- Die Datei wird automatisch automatisch entpackt und das Update wird durchgeführt.

Step 4 — Überprüfen der installierten Version



- Wählen Sie in dem Duet Web Control folgende Schaltflächen aus:
 - Settings
 - General
 - ablesen der installierten Version
- ❗ Hier sollte nun die aktualisierte Versionsnummer stehen.
- ❗ Das Update wurde erfolgreich durchgeführt.

